

Cum sa substitui pachetul Toshiba Bluetooth cu pachetul Microsoft Bluetooth



Unele Computere personale sau dispozitive Bluetooth utilizeaza pachetul Toshiba Bluetooth Stack. Acest pachet Bluetooth poate cauza erori ale PC-ului in timpul rularii aplicatiei software Parrot Flash Update Wizard.

Acest document explica cum sa inlaturam pachetul Toshiba Bluetooth Stack si cum sa il inlocuim cu cel Microsoft Bluetooth Stack care este compatibil cu software-ul Parrot Flash Update.

Pentru a putea folosi pachetul Microsoft Bluetooth Stack, Windows XP Service Pack 2 trebuie sa fie instalat in PC-ul dvs. Pachetul Microsoft Bluetooth Stack este inclus in acest pachet software.


1 . How to make sure that Windows XP Service Pack 2 is installed on your PC?

To make sure that Windows XP Service Pack 2 is installed on your PC, please follow the process below:

- Click on the Windows START button, consult the CONTROL PANEL.



- Click on the SYSTEM icon.




- On the GENERAL tab, the version of your Operating System is displayed




- If you don't have Windows Service Pack 2, please update your PC or consult the Microsoft Corporation web site: <http://www.microsoft.com>

2 . Removing the Toshiba Bluetooth Stack.


- Click on the Windows START button, and then consult the CONTROL PANEL.



- Click on the ADD / REMOVE PROGRAMS icon.




- Select the Toshiba Bluetooth Stack and remove this program.



3 . Set the Microsoft Bluetooth Stack as default one.


- Click on the Windows START button and select the RUN command



- Enter the following command: `%windir%\inf`



- On the current windows check if the **bth.bak** file exists and rename it into **bth.inf**.
If the file doesn't exist, please pass this step.



- Restart your PC.



- The Microsoft Bluetooth Stack has been defined as default one. The Parrot Flash Update Wizard will use this new Bluetooth Stack. In order to perform an update, please consult the Update documentation on our web site: www.parrot.biz in the SUPPORT \ DOWNLOAD section.